

# Updating the SIT Add-In

If SIT is not being properly updated, you must completely uninstall SIT from ArcMap.

1. Launch **ArcMap**.
2. In the toolbar, click **Customize > Add-In Manager** (Figure 1).




Figure 1. Customize and Add-in Manager

3. In the Add-In Manager, click on the **Options** tab (Figure 2).
4. Remove all folder references that contain SIT Add-Ins. Please note that if ArcMap is not letting you delete a folder, check your file system to make sure the directory exists. If it does not, create the folders to match the path in ArcMap. Reopen the Add-In Manager and ArcMap will now let you delete the folder reference.




Figure 2. Removing folders.

5. In the Add-In Manager, click on the **Add-Ins** tab (Figure 3).
6. If the SIT Add-In exists, click on **Delete this Add-in** (Figure 3).
7. A pop-up will appear asking if you wish to delete this Add-in. Select **Yes**.




Figure 3. Deleting an Add-In.

8. On the bottom of the Add-In Manager, click on **Customize...**
9. Anywhere you have a SIT Add-In in the toolbar, use your mouse to drag the SIT Add-In outside of the toolbar until an X pops up (Figure 4). This will remove the SIT Add-In.




Figure 4. Removing the SIT Add-In from the toolbar.

10. Close your ArcMap application.

11. Follow instructions at the [DATIM SIT homepage https://apps.fs.usda.gov/datim/sit/Index](https://apps.fs.usda.gov/datim/sit/Index) on how to install SIT.
12. **IMPORTANT:** In the folder that contains your newest SIT Add-In, make sure only one SIT Add-In file exists in it (Figure 5). If there is more than one you must delete all other SIT Add-In files from your connected folder.




Figure 5. SIT Add-In in your folder.

## How to Check the Installed Version of SIT

### Options #1.

1. Launch **ArcMap**.
2. Hover your mouse over a SIT Add-In without clicking on it.
3. Press **F1** on your keyboard (Figure 6).




Figure 6. SIT version on the toolbar.

### Option #2.

1. Launch **ArcMap**.
2. In the toolbar, click **Customize > Add-In Manager**, then click on SIT (Figure 7).




Figure 7. SIT version on the Add-In Manager.

### Option #3.

1. Launch **ArcMap**.
2. Launch **SIT** and completely log in.
3. Read the last modified and version number on the bottom of SIT (Figure 8).



Figure 8. SIT version on the bottom of SIT.



Figure 9. Section 508 Accessibility Seal